DownloadOrderFromPlatform

request

manufacturer	
type	string
occurs	0..1
description	the supplier code (see company list)

customerid	
type	string
occurs	1
description	the username that was given to the customer to access this webservice; usually this is the customer number

username	
type	string
occurs	0..1
description	the username that was given to the customer to access this webservice; this is only used if a username and a customer number needs to be transmitted

password	
type	string
occurs	1
description	the password that was given to the customer to access this webservice; this is transfered in plaintext

referenceNo	
type	string
occurs	1
description	the value of referenceNo (b2boptic → items → item) of the order that was send by the client with UploadOrderToPlatform

```
<xsd:element name="DownloadOrderFromPlatform">
  <xsd:complexType>
    <xsd:complexContent>
      <xsd:extension base="b2b:Ws_AuthenticationType">
        <xsd:sequence>
          <xsd:element name="referenceNo" type="xsd:string" />
        </xsd:sequence>
      </xsd:extension>
    </xsd:complexContent>
  </xsd:complexType>
</xsd:element>
<xsd:complexType name="Ws_AuthenticationType">
  <xsd:sequence>
    <xsd:element name="manufacturer" type="xsd:string" minOccurs="0" />
    <xsd:element name="customerid" type="xsd:string" />
    <xsd:element name="username" type="xsd:string" minOccurs="0" />
    <xsd:element name="password" type="xsd:string" />
  </xsd:sequence>
```

```
</xsd:complexType>
```

response

b2bxmlorder (part of choice)	
type	string
occurs	1
description	the order in B2BOptic LensOrder 1.6.0 format; the xml document is included in a CDATA-section (http://www.w3.org/TR/REC-xml/#dt-cdsection)

b2bxmlinfo (part of choice)	
type	string
occurs	1
description	the status info about the order in B2BOptic LensInfo 0.3.0 format; the xml document is included in a CDATA-section (http://www.w3.org/TR/REC-xml/#dt-cdsection)

errorCode (part of choice)	
type	int
occurs	1
description	an error code from server

errorText (part of choice)	
type	string
occurs	1
description	a description for the error by the server

errorTextUser (part of choice)	
type	string
occurs	0..1
description	a error description text in native language of the user, that the client can display

```
<xsd:element name="DownloadOrderFromPlatformResponse">
  <xsd:complexType>
    <xsd:choice>
      <xsd:sequence>
        <xsd:element name="b2bxmlorder" type="xsd:string" />
        <xsd:element name="b2bxmlinfo" type="xsd:string" />
      </xsd:sequence>
      <xsd:sequence>
        <xsd:element name="errorCode" type="xsd:int" />
        <xsd:element name="errorText" type="xsd:string" />
        <xsd:element name="errorTextUser" type="xsd:string" minOccurs="0" />
      </xsd:sequence>
    </xsd:choice>
  </xsd:complexType>
</xsd:element>
```

From:
http://wiki.b2boptic.com/ - **wiki.b2bOptic.com**

Permanent link:
http://wiki.b2boptic.com/en:webservice:version010000:structure:downloadorderfromplatform

Last update: **2013/06/05 10:12**